Bit Shifts

ICS312

Machine-Level and Systems Programming

Henri Casanova (henric@hawaii.edu)

Why bitwise operations?

- Some of the coolest “tricks” in programming rely on bitwise operations, *regardless of the programming language*
  - With only a few instructions one can do a lot very quickly using judicious bit operations
  - Heavily used in fast algorithm implementations (and thus in programming competitions)
- High-level languages almost all offer bitwise operators to manipulate bits
- And you can do even more in assembly

- A common bitwise operation: shifting

Shift Operations


- A shift moves the bits around in a value
- A shift can be toward the left (i.e., toward the most significant bits), or toward the right (i.e., toward the least significant bits)



- There are three main kinds of shifts
  - logical shifts
  - arithmetic shifts
  - rotate shifts (typically not directly available in high-level languages)

Logical Shifts

- Logical shifts are the simplest: bits disappear at one end and zeros appear at the other



Logical Shift Instructions

- Two instructions: **shl** and **shr**
- One must specify by how many bits the data is shifted
  - Either by just passing a constant to the instruction
  - Or by using whatever is stored in the **CL** register
  - One can shift by at most 31 bits
- After the instruction has executed, the carry flag (CF) contains the **last bit** that was shifted out
- Example:

```
mov al, 0C6h          ; al = 1100 0110
shl al, 1             ; al = 1000 1100 (8Ch)   CF=1
shr al, 1             ; al = 0100 0110 (46h)   CF=0
shl al, 3             ; al = 0011 0000 (30h)   CF=0
mov cl, 2
shr al, cl            ; al = 0000 1100 (0Ch)   CF=0
```

Left Shifts to Multiply

- Common use of left shifts: **quickly multiply by powers of 2**
- In decimal:
  - Multiply 13 by 10: add one 0 to the right to get 130
  - Multiply 13 by $100=10^2$: add two 0's to the right to get 1300
  - "adding 0's the the right" is a left shift!!
- In binary
  - Multiply 101 by 2: add one 0 to the right to get 1010
  - Multiply 101 by $4=2^2$: add two 0's to the right to get 10100

- This is always true mathematically, but in computer arithmetic we have a limited number of bits
  - We may not have enough bits to store the numerical result
- For instance, consider the UNSIGNED 8-bit value 10000000 (128d)
- Multiplying by 2 with a left shift gets us: 00000000, which is not right
  - We cannot encode 256d with 8 bits because $256 > 2^8-1$
  - It's a kind of overflow

Right Shifts to Divide

- Common use for right shifts: **quickly divide by powers of 2**
- In decimal, for instance:
  - Divide 1300 by 10 is really one right shift to obtain 0130
  - Divide 1300 by $100=10^2$ is really two right shifts to obtain 0013
- In binary
  - Divide 1100 by 2 is really a right shift to obtain 0110
  - Divide 1100 by $4=2^2$ is really two right shifts to obtain 0011
- When dividing odd numbers by 2 we “lose bits”, which ends up rounding to the integer division’s quotient (the remainder ends up in the carry flag!)
- For example:
  - Consider the binary number 10011 (19d)
  - One right shift: 01001 (9d: 19/2 rounded below)
  - Another right shift: 00100 (4d: 9/2 rounded below)

What about Signed Numbers?

- In the previous slides, we have implicitly assumed unsigned numbers
- Things are not as simple for signed numbers
  - Are they ever?
- When numbers are signed, the shifts may not handle the *sign* bit correctly
  - This is because logical shifts treat the sign bit like any other bit, but for signed numbers it's a special bit
  - As a result, the number may change sign due to the shift, which produces a numerically incoherent result
- Let's see this on two examples…

What about Signed Numbers?(2)

- Left shift example: Consider the 1-byte number 63h
  - If unsigned:
    - 63h = 99d = 01100011b
    - left shift: 11000110b = C6h = 198d (which is 99 * 2)
  - In signed:
    - 63h = 99d = 01100011b
    - left shift: 11000110b = C6h = -58d (which is NOT 99 * 2)
- Right shift example: Consider the 1-byte number FE
  - If unsigned:
    - FEh = 254d = 11111110b
    - right shift: 01111111b = 7Fh = 127d (which is 254/2)
  - In signed:
    - FEh = - 2d = 11111110b
    - right shift: 01111111b = 7Fh = +127d (which is NOT -2/2)

Arithmetic Shifts

- Since the logical shifts do not always work for signed numbers, we have another kind of shifts called arithmetic shifts
- Left arithmetic shift: sal
  - This instruction works just like shl
    - We just have another name for it so that in the program we "see/remember" that we're dealing with signed numbers
  - As long as the sign bit is not changed by the shift, the result will be correct (i.e., will be multiplied by 2)
- Right arithmetic shift: sar
  - This instruction does NOT shift the sign bit: the new bits entering on the left are copies of the sign bit
- Both shifts store the last bit out in the carry flag

Arithmetic Shift Example

- If **signed numbers**, then the operations below are correct multiplications / divisions of 1-byte quantities

```
mov    al, 0C3h      ; al = 1100 0011   (-61d)
sal    al, 1         ; al = 1000 0110   (86h = -122d)
sar    al, 3         ; al = 1111 0000   (F0h = -16d)
     ; (note that this is not an exact division as we
     ;  lose bits on the right… rounding occurs)
```

- Let's say that now I want to multiply the value above by 16
- I cannot do a left shift by 4 = log(16) bits: I'd get 0 because I'd lose all bits
- Instead, I should use the **`imul`** instruction instead (but unfortunately **`imul`** doesn't work on 1-byte quantities):

```
movsx       ax, al        ; sign extension!
imul        ax, 16        ; result in ax
```

- Let's see/run this example in file ics312_arithmetic_shift.asm

In-Class Exercise

- Consider the following instructions

```
mov   ax, 0F471h
sar   ax, 3
shl   ax, 7
sar   ax, 10
```

- At each step, give the content of register ax (in hex and binary) and the value of CF (assuming that initially it is equal to 0)
  - Remember: CF contains the last bit that was shifted out

In-Class Exercise


```
mov     ax, 0F471h
          ax = 1111 0100 0111 0001
          ax = F471h                                  CF=?
                                        (whatever it was before)
sar     ax, 3
          ax = 1111 1110 1000 1110
          ax = FE8Eh.                                 CF=0
shl     ax, 7
          ax = 0100 0111 0000 0000
          ax = 4700h                                  CF=1
sar     ax, 10
          ax = 0000 0000 0001 0001
          ax = 0011h                                  CF=1
```

Rotate Shifts

- `rol` and `ror`: circular left and right shifts
  - bits shifted out at one end are shifted in at other end
- Example:

```
mov   ax, 0F471h
          ax = 1111 0100 0111 0001
          ax = F471h

 ror  ax, 3
          ax = 0011 1111 1101 0001
          ax = 3FD1h
```



Example Using Shifts

- Let's do Example 3.1.5 in the book: say you want to count the number of bits that are equal to 1 in register EAX
  - This is useful because often we encode sets as bits (e.g., a bit set to 1 means an element is present)
  - Which saves a lot of space when compared to, say, an array of booleans
- One easy way to do this is to use shifts
  - Shift 32 times (left or right, doesn't matter)
  - Each time the carry flag contains the last shifted bit
  - If the carry flag is 1, then increment a counter, otherwise do not increment a counter
- Let's write this in x86 assembly live right now…
  - The textbook uses the loop instruction, so let's write it without it
  - On the next slide is something that should look a lot like what we're about to implement…

Example Using Shifts

```
; Counting 1 bits in EAX
  mov  bl, 0      ; bl: the number of 1 bits
  mov  cl, 32     ; cl: the loop counter
loop_start:
  shl   eax, 1    ; left shift
  jnc   not_one   ; if carry != 1, jump to not_one
  inc   bl        ; increment the number of 1 bits
not_one:
  dec cl          ; decrement the loop counter
  jnz loop_start  ; if more iterations then
                  ; goto loop_start
```

The same, with the adc instruction

- Convenient instruction: adc (add carry)
  - `adc dest, src ; dest += src + cf`

```
; Counting 1 bits in EAX
    mov  bl, 0   ; bl:the number of 1 bits
    mov  cl, 32  ; cl: loop counter
loop_start:
   shl     eax, 1 ; left shift
   adc     bl, 0  ; add the carry to bl
   dec     cl     ; decrement the loop counter
   jnz loop_start ; if more iterations then
                  ; goto loop_start
```

The same, with the loop instruction

- Remember the loop instruction
  - `loop <label> ; decrements loop index (in ecx)`
    `; and branches if ecx isn't 0`

```
; Counting 1 bits in EAX
    mov   bl, 0    ; bl: the number of 1 bits
    mov   ecx, 32  ; ecx: the loop counter
loop_start:
   shl    eax, 1     ; left shift
   adc bl, 0         ; add the carry to bl
   loop loop_start   ; decrement ecx and
                     ; then loop if needed
```

Making it more efficient?

- Anybody has an idea about how to make this code more efficient?

Making it more efficient?

- Anybody has an idea about how to make this code more efficient?
- Let's consider an example:
  - Say that EAX = 40 00 00 00 h (a single 1 bit)
  - Yet, we iterate 32 times… doesn't that seem like a waste?
  - So, anybody has any thoughts on how to avoid iterating 32 times?

Making it more efficient?

- Anybody has an idea about how to make this code more efficient?
- Let's consider an example:
  - Say that EAX = 40 00 00 00 h (a single 1 bit)
  - Yet, we iterate 32 times… doesn't that seem like a waste?
  - So, anybody has any thoughts on how to avoid iterating 32 times?

- Simple idea: stop when EAX == 0

Likely the best version

```
; Counting 1 bits in EAX
    mov     bl, 0     ; bl: the number of 1 bits
loop_start:
    shl     eax, 1        ; left shift
    adc     bl, 0         ; add the carry to bl
    cmp     eax, 0
    jnz     loop_start ; loop back if eax != 0
```

The code isn't shorter, but we don't waste any register to store a loop counter, as this is now a **while** loop!

(this idea could of course be used in high-level code as well)

Could be improved further (should do no work if EAX = 0)

The POPCNT instruction

- It turns out that x86 has an instruction to do the bit counting
  - `popcnt  eax, ebx`
    - EAX is set to the number of bits sets to one in EBX
- The x86 designers deemed this operation useful enough that they implemented it in hardware
  - Introduced circa 2008, so relatively recently
- And it can be accessed in high-level languages via compiler “intrinsics”
  - i.e., built-in functions that are not part of the language but that will call the assembly instruction for you
  - Not portable

Important Takeaways

- Three kinds of shifts:
  - Logical shifts: always shift in zeros
  - Arithmetic shifts: when to the right, will shift in replicas of the sign bit
  - Rotate shifts: treats the bits as in a circular buffer
- Right shifts divide, left shifts multiply
  - By powers of 2 only (of course)
  - Right logical shifts for unsigned division, right arithmetic shifts for signed division

Conclusion

- Bitwise operations are useful in general
  - It can be the bread-and-butter of the clever assembly/C/Java/Python/* programmer
    - See the FIRST programming question in Cracking the Coding Interview!!! (we'll do it in class)
  - It's often the only way to do things efficiently for some problems (as seen in many programming competitions!)
  - It is needed when dealing with data that's encoded in binary (e.g., images, sound, video)
- A few practice problems are posted
  - Let's briefly look at them, and try to do the "mystery program" questions in there as well…
- In the next set of lecture notes we'll talk about other bitwise operations and the use of bitmasks